

## Installera PigWin på nätverk och arbetsstationer

Innan installationen görs på arbetsstationerna måste pig\_win-mappen delas ut så att alla användare har fulla läs- och skrivrättigheter till den. Om hela enheten redan är delad är det förstås tillräckligt.

### **Server:**

Installera i mappen pig\_win

Genväg:

Mål: C:\PIG\_WIN\PIGWIN.EXE

Starta i: C:\PIG\_WIN\

På arbetsstationen måste den delade enheten eller mappen vara "mappad" dvs. tilldelad en enhetsbokstav. I följande exempel är c: på servern tilldelad s: på arbetsstationen

### **Arbetsstation:**

*Program lokalt, data på server*

Genväg:

Mål: C:\PIG\_WIN\PIGWIN.EXE S:\PIG\_WIN\REG\_FIL

Starta i: C:\PIG\_WIN\

*Program och data på server:*

Genväg:

Mål: S:\PIG\_WIN\PIGWIN.EXE

Starta i: S:\PIG\_WIN\

För att programmet ska köra korrekt måste följande program installeras:

### **Btrieve 6.15**

Kontrollera under Kontrollpanelen – Lägg till/ta bort program om version 6.15 av databashanteraren Btrieve är installerad. Installera annars Btrieve 6.15 på båda datorerna, se information på följande länk: [www.pigwin.se/btrieve](http://www.pigwin.se/btrieve).

### **Inställningar**

The most important is that the computer who has the PigWin database has the database manager set up for local file sharing. It has to be ON.

Please follow this guide and it will get you to the goal. Please run the below on both computers.

- 1 Make sure that WinPig.16 and the W32MKDE.EXE are closed (Job list).
- 2 Click Start and Run and write [path to the PigWin.16 folder]\w32mkde.exe -reginstall and click OK.
- 3 A window opens and a text saying Default setting is used is displayed. Close this window.
- 4 Click Start and Run and write REGEDIT and click OK.
- 5 Open "HKEY\_LOCAL\_MACHINE\SOFTWARE" and right click on "Btrieve Technologies" and select Permissions.

- 6 Give full control to all the users possible. Some, like admin and system, will not allow it but they already have full rights. End by clicking OK
- 7 Now click on the + in front of "Btrieve Technologies" and then on the + in front of "Microkernel Workstation Engine" and on the + in front of "Version 6.15" and then click on "Settings".
- 8 Three things have to be changed here: "Create 5x Files", "File Sharing On Local Drive" and "Home Directory". Before changing them they must have the Data value "0", "0" and "C:\Windows". If not or if the "Home Directory" is not found then close the window and do number 2, 3, 7 and 8 again until the setting are showing the right figures.
- 9 Now the three items have to be reset. Double click on each of the three items in turn and enter the following: "Create 5x Files" set to "1", "File Sharing On Local Drive" set to "1" (**ONLY ON THE COMPUTER WHERE THE DATABASE IS PLACED**) and "Home Directory" set to "[PigWin.16 path]. This would normally be C:\PIG\_WIN.